



## Setting up your new YourLink email account in Microsoft Outlook Express

1. Open up your Outlook Express. If no account is existing you will be presented with the following.




The screenshot shows the 'Your Name' step of the Internet Connection Wizard. The window title is 'Internet Connection Wizard'. The main heading is 'Your Name'. Below the heading, there is a text box containing 'John Doe'. To the left of the text box is the label 'Display name:'. Below the text box is the text 'For example: John Smith'. At the bottom of the window, there are three buttons: '< Back', 'Next >', and 'Cancel'. The 'Next >' button is highlighted.

2. Enter your name. This will be the name that will be displayed in the from field on the emails you send.




The screenshot shows the 'Internet E-mail Address' step of the Internet Connection Wizard. The window title is 'Internet Connection Wizard'. The main heading is 'Internet E-mail Address'. Below the heading, there is a text box containing 'john.doe@rctvonline.net'. To the left of the text box is the label 'E-mail address:'. Below the text box is the text 'For example: someone@microsoft.com'. At the bottom of the window, there are three buttons: '< Back', 'Next >', and 'Cancel'. The 'Next >' button is highlighted.

3. Enter your YourLink email address
4. Click "Next ".



The screenshot shows the 'Internet Connection Wizard' window with the 'E-mail Server Names' tab selected. The window title is 'Internet Connection Wizard'. The main heading is 'E-mail Server Names'. Below the heading, there is a dropdown menu set to 'POP3' with the text 'My incoming mail server is a POP3 server.' Below this, there is a text box labeled 'Incoming mail (POP3, IMAP or HTTP) server:' containing the text 'mail.rctvonline.net'. Below that, there is a text box labeled 'Outgoing mail (SMTP) server:' also containing 'mail.rctvonline.net'. At the bottom of the window, there are three buttons: '< Back', 'Next >', and 'Cancel'. A mouse cursor is pointing at the 'Next >' button.

5. Select POP3 as your incoming mail server.
6. Set "Incoming mail (POP3, IMAP or HTTP) server" to mail.rctvonline.net
7. Set "Outgoing mail (SMTP) server" to mail.rctvonline.net
8. Click "Next".




The screenshot shows the 'Internet Connection Wizard' window with the 'Internet Mail Logon' tab selected. The window title is 'Internet Connection Wizard'. The main heading is 'Internet Mail Logon'. Below the heading, there is a text box labeled 'Account name:' containing the text 'john.doe@rctvonline.net'. Below that, there is a text box labeled 'Password:' containing a series of dots. Below the password box, there is a checked checkbox labeled 'Remember password'. Below that, there is a text box labeled 'Log on using Secure Password Authentication (SPA)' which is unchecked. At the bottom of the window, there are three buttons: '< Back', 'Next >', and 'Cancel'. A mouse cursor is pointing at the 'Next >' button.

Enter your YourLink full email account as your Account name


10. Enter your YourLink password. If you don't remember your password please contact your YourLink office to have it reset.

11. Click "Next".


12. The initial account is setup but we still need to setup authentication for sending. Go to "Tools" -> "Accounts..."



13. Select the "Mail" tab and select your account from the list.



6. A properties page will display. Select the Servers tab.
7. Click the "My Server Requires Authentication".
8. Click "OK".



Congratulations you have just setup your Yourlink email account through outlook express.